


# WILBOR MP3 Audiobooks on a Kindle (Using a PC)

WILBOR Guides



Updated 5-29, 2012

MP3 audiobooks (not wma) can be transferred to a Kindle Keyboard or Kindle Touch. The basic Kindle does not support audio. (For instructions on downloading mp3 audiobooks to a Kindle Fire, see the WILBOR Guide “Audiobooks on the Kindle Fire.”)


1. Check out and download the mp3 title to the Overdrive Media Console on your PC. Click on the title in the library list in OMC (it will highlight in blue) and click on the “Transfer” button.




2. Connect the Kindle to the computer using the USB cable. (The Kindle should be powered on.) Click on “Next.” On the screen at which you can select the parts you wish to transfer, click on “Advanced Options.”




3. Click on the “Browse” button.








4. Browse to find, and click on, the “documents” folder on the ‘Kindle.’ The Advanced Options will then show “/documents” in the Player folder. Click on OK.



5. At the Transfer Wizard Window, click on “Next,” and the transfer will proceed. When the transfer is complete, click on “Finish” and properly disconnect the Kindle.



6. The parts of the book will appear on your Kindle’s Home menu, with “audio” to the left of the title.







## These might come up:

I didn't do the "Advanced" options before I downloaded so I know it's on the Kindle but I can't find it. Now what do I do?


1. In "My Computer" or Windows Explorer, locate "Kindle" as an external drive. (Here it is F: but it might be a different drive letter on your computer), and double click on the Kindle drive to open it.



2. The parts of the audiobook will appear in the root directory of the Kindle. You want the parts to be in the "documents" folder, so select the parts, and drag-and-drop them into the "documents" folder. (To select all the parts at once, click on the first part, then Shift-Click on the last part.)



3. The audiobook is now in the “documents” folder. [Disconnect your kindle, using the “Safely Remove Hardware and Eject Media” in your system tray at the very bottom right of your computer screen.]



4. When you look at the “Home” on your Kindle, you will see the audiobook at the top of the list. (It will appear in parts, not as a single title.)

