


Adobe Digital Editions 2.0

WILBOR Handy Guides

Updated 2/8/2013

If you wish to download an eBook from WILBOR and transfer to a nook, Sony Reader, Pandigital, or similar devices (NOT Kindle, iDevices, smartphones or Android tablets) you will first need to download and install Adobe Digital Editions on your computer.

1. On the WILBOR website (<http://wilbor.lib.overdrive.com>), scroll down on the left to “Digital Software” and click on “Adobe Digital Editions.”



2. Click on “Download Adobe Digital Editions” and then, on the Adobe website, click on the “Download Digital Editions” in the Getting Started section follow instructions to install.

Help - Software - Adobe eBooks



[Download Adobe Digital Editions](#)

Getting Started

Follow these steps to get started with the Adobe Digital Editions:

- [Download Adobe Digital Editions >](#)
- Run the installer and follow the on-screen instructions.
- Once installed, open the *Getting Started* eBook for an overview of the application.

3. When you open Adobe Digital Editions after it has been downloaded and installed, you will see an authorization screen.



4. If you wish to transfer books borrowed from WILBOR to a portable device you will need to activate the computer and the device with your Adobe ID . If you need an Adobe ID, click on “Create an Adobe ID ” on the authorization screen, and follow instructions.


5. To activate Adobe Digital Editions and authorize the computer, enter your Adobe ID and password and click on “Authorize.”



6. The first time you connect your ereader device after installing Adobe Digital Editions, a window will pop up, with instructions for authorizing that device. Follow instructions.

After installing and authorizing Adobe Digital Editions, when you click on “Download” for a book in your WILBOR “My Items Out” list, Adobe Digital Editions will automatically open and the book will download into the “Read” view.

To transfer the ebook to your ereader device:



1. Connect your device;
2. Make sure you are in the “Library” view in Adobe Digital Editions;
3. Click and hold the mouse button on the book’s cover, and drag on top device’s icon in the Bookshelves in Adobe Digital Editions.




These might come up:

When I plug my ereader into the computer's USB port, the device doesn't appear in Adobe Digital Editions.

Your computer/Adobe Digital Editions and your ereader device must be authorized with the same Adobe ID.

To authorize the computer, with Adobe Digital Editions open pull down the "Help" menu and select "Authorize computer," or press the key combination: Ctrl+Shift+U



If the computer is authorized, but not with correct Adobe ID, deauthorize the computer first:

1. Open Adobe Digital Editions
2. On a PC press: Ctrl+Shift+D (press all 3 keys at the same time); On a Mac: Cmd+Shift+D)
3. Deauthorize screen will open, and warn you that protected items in your library may no longer be readable
3. Select Deauthorize, then Click on Quit
4. Authorize computer as described above.



The device & ADE are both authorized with the same Adobe ID, but I still can't see the device.

Try disconnecting the device, and closing Adobe Digital Editions. Connect the device again, then open Adobe Digital Editions. Sometimes the order in which you do things matters!